

Configure Products

Create a new product or edit the existing server product. Click on **Module Settings** and choose **Dedicated Server** at Module Name. After choosing the module, additional configuration fields will be loaded, which are explained below.



Auto Setup

Select "Automatically setup the product as soon as the first payment is received" if deployments should be processed automatically.

Dedicated Server Products

If the product is a dedicated server, choose **Dedicated** at the option Server Type.

| | | | | | | | | |
|-------------|---------|------------------|---------------|----------------------|----------|-------------|---|-------|
| Details | Pricing | Module Settings | Custom Fields | Configurable Options | Upgrades | Free Domain | Other | Links |
| Module Name | | Dedicated Server | | | | | Server Group | |
| Server Type | | Dedicated | | | | | Choose if product is a dedicated server or VPS. | |

Virtual Server (VPS) Products

If this product is a virtual server (VPS), choose **VPS** at the option Server Type and click **Save Changes**. After saving, a new field will appear which shows your hostsystems. Select the hostsytem on which you want to auto setup the VPS products and click **Save Changes** again.

New configuration options will be shown which allows you to set the ressources of this product.

The following options can be setted:

- Diskspace
- Memory (RAM)
- CPU Cores
- Network interface (vibr0, etc.)
- Datastore

| | | | | | | | | | | |
|-----------------|---------------|----------------------|----------|-------------|---|-------|-----|------------|-----------------------------|-------------------------------|
| Module Settings | Custom Fields | Configurable Options | Upgrades | Free Domain | Other | Links | | | | |
| Module Name | | Dedicated Server | | | Server Group | | ded | | | |
| Server Type | | VPS | | | Choose if product is a dedicated server or VPS. | | | Hostsystem | proxmox-test1 (10.20.43.85) | Select the hostsytem |
| Disk Space | | 1000 | | | MB. Enter the disk space size in MB. | | | Memory | 2000 | MB. Enter the RAM size in MB. |
| CPU Cores | | 4 | | | Cores. Enter the amount of CPU Cores. | | | Network | vibr0 | Choose network interface. |
| Datastore | | test-3 | | | Choose the datastore location. | | | | | |



At the IP Manager you can assign the subnets to your hostsystems.